

# POOLcontrol-40.NET<sup>®</sup>


## Updating the software in the control unit

The software in the PC-40.net is constantly being developed, expanded and adapted to changing needs. In order for the owners of older devices to be able to participate in this technical progress, the PC-40.net has the option of updating the software in the control even after delivery.

Only a few steps are required for such an update:

1. Disconnect PC-40.net from the power supply.
2. Remove the front cover.
3. Remove the memory card from the board.
4. Download the ZIP archive with the update files from [http://osf.de/download/download.php?dll=Kundenbereich/Updates/PC40\\_update.zip](http://osf.de/download/download.php?dll=Kundenbereich/Updates/PC40_update.zip).
5. Unpack all files and directories from the ZIP archive and copy them to the memory card.
6. Insert modified memory card into the socket on the board.
7. Re-mount the front cover.
8. Switch the power supply on again.

The update process will start automatically.



**The electrical connection as well as the work of adjustment and servicing should be carried out only by an approved electrician.**

For a video demonstration of the procedure, see

[https://osf.de/download/download.php?dll=Netzwerk/Softwareupdate\\_PC40.net\\_en.mp4](https://osf.de/download/download.php?dll=Netzwerk/Softwareupdate_PC40.net_en.mp4).



**osf Hansjürgen Meier . Elektrotechnik und Elektronik GmbH & Co KG**

Postfachanschrift:  
Postfach 1405  
D-32328 Espelkamp

Hausanschrift:  
Eichendorffstrasse 6  
D-32339 Espelkamp

Telefon (05772) 9704-0  
Telefax (05772) 5730

E-Mail: [info@osf.de](mailto:info@osf.de)  
Internet: [www.osf.de](http://www.osf.de)

